



Ulu Potholders (makes set of 2)

Supplies:

Body and top edge templates

10" x WOF Front and Back of potholder

9" x WOF Pocket

9" x 22" Insul-bright. Cut in half for 2 – 9 x 11" pieces

9" x 22" Regular batting. Cut in half for 2 – 9 x 11" pieces

2 pieces of 2" x 5" fabric for hanging loops, either of above fabric

*WOF is width of fabric

Make pocket first:

Cut 4 pockets from 9" x WOF fabric, being mindful of directional patterns. With right sides together, sew along the top (flat) edge. Turn right sides out, press and topstitch $\frac{1}{4}$ " from edge.



Front and Back:

Once pocket pieces are cut, tape the top edge ($1 \frac{1}{2}$ " x $6 \frac{1}{2}$ ") to the top of the pocket pattern to make Front and Back pattern. Cut 4 (2 front, 2 back) from the 10" x WOF fabric piece. As with the pocket, be mindful of directional fabric.



Layering for sewing, from the bottom up:

Insul-Bright 9" x 11"..... Leave batting in rectangle shape until after sewing

Regular batting 9" x 11".... " " " " " " " "

Back of potholder – face up

Pocket - face down

Front of potholder – face down

Leaving top edge open for turning, sew $\frac{1}{4}$ " from edge all the way around, starting at top and reinforcing points of the Ulu

Trim the batting, clip curves and trim points. Turn right side out.

Turn under the top edge by $\frac{1}{2}$ " and press all around.

Make hanging loops:

Using the 2" x 5" strips, fold each in half lengthwise, wrong sides together and press to crease.

Open up and fold each outside edge to the center, meeting at the crease.

Then fold one side over to meet the other press, and topstitch close to the open edge.

Insert hanging tabs into left corner of top edge and top-stitch all the way around the potholder.

